

Yellowfin Configuration

- [Overview](#)
- [General System Settings](#)
 - [Java Path](#)
 - [Application Name](#)
 - [Application .war File Name](#)
 - [Application Log File Name](#)
 - [Base Tags Option](#)
 - [Date Format](#)
 - [Export Filename](#)
 - [Support Email Address](#)
 - [Use UserId Authentication](#)
 - [Adding Additional Files](#)
- [Administrator User](#)
 - [Administrator Username](#)
 - [Administrator User Password](#)
 - [Administrator User First Name](#)
 - [Administrator User Last Name](#)
 - [Administrator User Email Address](#)
- [LDAP Settings](#)
 - [LDAP Bind Username](#)
 - [LDAP Bind Password](#)
- [Broadcast Email](#)
 - [Broadcast Email Address](#)
 - [Broadcast Email Name](#)
- [SMTP Server](#)
 - [SMTP Server Hostname](#)
 - [SMTP Server Port](#)
 - [SMTP Server SSL Option](#)
 - [SMTP Server StartTLS Option](#)
 - [SMTP Server Authentication](#)
 - [SMTP Server Username](#)
 - [SMTP Server Password](#)
- [Dashboard Settings](#)
 - [Dashboard Width](#)
 - [Dashboard Associated Reports Location](#)
 - [Dashboard Analytic Filter Location](#)
 - [Dashboard Search Location](#)
- [Navigation Settings](#)
 - [Show Toolbar](#)
 - [Show Logoff Link on Toolbar](#)
- [Integration Settings](#)
 - [Custom Index Page](#)
 - [Header Type](#)
 - [Standard Header URL](#)
 - [Custom Header URL](#)
 - [Footer Type](#)
 - [Standard Footer URL](#)
 - [Custom Footer URL](#)
- [Best Practice Tips](#)

Overview

[top](#)

These properties modify the default configuration of the Yellowfin installation, post-install.

General System Settings

Java Path

Property	option.javahome
Value	The location of the java installation that should be used to run Yellowfin. If this is not set, the java installation used to run the installer will be used.

Example	<code>option.javahome=/usr/lib/jvm/java-6-sun</code>
----------------	--

Application Name

Property	<code>action.config.appname</code>
Value	The application name that is displayed within the application, instead of "Yellowfin".
Default	Yellowfin
Example	<code>action.config.appname=BI Blue</code>

Application .war File Name

Property	<code>installer.warfilename</code>
Value	The name of the web application archive (.war) file.
Default	yellowfin.war
Example	<code>installer.warfilename=reports.war</code>

Application Log File Name

Property	<code>installer.applogfilename</code>
Value	The name of the application log file. Yellowfin logs to this file during normal operation.
Default	yellowfin.log
Example	<code>installer.applogfilename=reports.log</code>

Base Tags Option

Property	<code>action.config.basetags</code>
Value	Whether <base> tags should be included in html within the Yellowfin. Should be YES, NO or COMMENT
Default	COMMENT
Example	<code>action.config.basetags=NO</code>

Date Format

Property	<code>action.config.dateformat</code>
Value	The default date format. Should be DMY, MDY or YMD.
Default	DMY
Example	<code>action.config.dateformat=MDY</code>

Export Filename

Property	<code>action.config.exportfilename</code>
Value	The filename used for XML content exports.
Default	YellowfinExport.xml

Example	<code>action.config.exportfilename=BIExport.xml</code>
----------------	--

Support Email Address

Property	<code>action.config.supportemail</code>
Value	The support email address. Error reports can be sent to this address.
Default	<code>support@yellowfin.com.au</code>
Example	<code>action.config.supportemail=support@example.com</code>

Use UserId Authentication

Property	<code>action.authentication.userid</code>
Value	If this is set to true, users log in with a UserId rather than an email address.
Default	<code>false</code>
Example	<code>action.authentication.userid=true</code>

Adding Additional Files

See [Adding Files to the Application](#) for more information.

Administrator User

Administrator Username

Property	<code>action.adminuser.username</code>
Value	The login username for the initial administrator user account.
Default	<code>admin@yellowfin.com.au</code>
Example	<code>action.adminuser.username=adminuser</code>

Administrator User Password

Property	<code>action.adminuser.password</code>
Value	The password for the initial administrator user account.
Default	<code>test</code>
Example	<code>action.adminuser.password=secret</code>

Administrator User First Name

Property	<code>action.adminuser.firstname</code>
Value	The first name for the initial administrator user account.
Default	<code>System</code>
Example	<code>action.adminuser.firstname=Joe</code>

Administrator User Last Name

Property	<code>action.adminuser.lastname</code>
Value	The last name for the initial administrator user account.
Default	Administrator
Example	<code>action.adminuser.lastname=Smith</code>

Administrator User Email Address

Property	<code>action.adminuser.email</code>
Value	The email address for the initial administrator user account.
Default	<code>admin@yellowfin.com.au</code>
Example	<code>action.adminuser.lastname=admin@example.com</code>

LDAP Settings

LDAP Bind Username

Property	<code>action.config.ldapbinduser</code>
Value	The default LDAP bind username.
Example	<code>action.config.ldapbinduser=username</code>

LDAP Bind Password

Property	<code>action.config.ldapbindpassword</code>
Value	The default LDAP bind password.
Example	<code>action.config.ldapbindpassword=secret</code>

Broadcast Email

Broadcast Email Address

Property	<code>action.config.broadcastemail</code>
Value	The email address that broadcast emails will be sent from.
Default	<code>no-reply@yellowfin.com.au</code>
Example	<code>action.config.broadcastemail=reports@example.com</code>

Broadcast Email Name

Property	<code>action.config.broadcastname</code>
Value	The from name for broadcast emails.

Default	Yellowfin Reports
Example	<code>action.config.broadcastname=BI Blue Reports</code>

SMTP Server

Following are the SMTP Server properties.



To learn how to configure an SMTP server, refer to [this section](#).

SMTP Server Hostname

Property	<code>action.config.smtpserver</code>
Value	The hostname of the smtp server to send mail through.
Example	<code>action.config.smtpserver=mail.example.com</code>

SMTP Server Port

Property	<code>action.config.smtpport</code>
Value	The smtp server port.
Example	<code>action.config.smtpport=465</code>

SMTP Server SSL Option

Property	<code>action.config.smtpssl</code>
Value	Set this to <code>true</code> to use SSL when connecting to the SMTP server.
Default	<code>false</code>
Example	<code>action.config.smtpssl=true</code>

SMTP Server StartTLS Option

Property	<code>action.config.smtpstarttls</code>
Value	Set this to <code>true</code> to use the StartTLS command when connecting to the SMTP server.
Default	<code>false</code>
Example	<code>action.config.smtpstarttls=true</code>

SMTP Server Authentication

Property	<code>action.config.smtpauth</code>
Value	Set this to <code>true</code> to use authentication when connecting to the SMTP server.
Default	<code>false</code>
Example	<code>action.config.smtpauth=true</code>

SMTP Server Username

Property	<code>action.config.smtpusername</code>
Value	The username used when authenticating with the SMTP server.
Example	<code>action.config.smtpusername=username</code>

SMTP Server Password

Property	<code>action.config.smtppassword</code>
Value	The password used when authenticating with the SMTP server.
Example	<code>action.config.smtppassword=secret</code>

Dashboard Settings

Dashboard Width

Property	<code>action.config.dashwidth</code>
Value	The default dashboard width in pixels.
Default	1000
Example	<code>action.config.dashwidth=800</code>

Dashboard Associated Reports Location

Property	<code>action.config.associatedreports</code>
Value	The position of associated reports on dashboards. Should be <code>RIGHT</code> or <code>OFF</code> .
Default	<code>RIGHT</code>
Example	<code>action.config.associatedreports=OFF</code>

Dashboard Analytic Filter Location

Property	<code>action.config.dashanalyticfilters</code>
Value	The default position of analytic filters on dashboards. Should be <code>LEFT</code> or <code>RIGHT</code> .
Example	<code>action.config.dashanalyticfilters=RIGHT</code>

Dashboard Search Location

Property	<code>action.config.searchlocation</code>
Value	The position of the search box on the dashboard page. Should be <code>TOP</code> , <code>RIGHT</code> or <code>OFF</code> .
Default	<code>TOP</code>
Example	<code>action.config.searchlocation=RIGHT</code>

Navigation Settings

Show Toolbar

Property	<code>action.config.showtoolbar</code>
Value	Set to <code>false</code> to disable the application toolbar on all pages.
Default	<code>true</code>
Example	<code>action.config.showtoolbar=false</code>

Show Logoff Link on Toolbar

Property	<code>action.config.showtoolbarlogoff</code>
Value	Set to <code>false</code> to disable the logoff link on the application toolbar.
Default	<code>true</code>
Example	<code>action.config.showtoolbarlogoff=false</code>

Integration Settings

Custom Index Page

Property	<code>action.customindexpage</code>
Value	<p>The location of a custom index page. This property points to a resource within the installer archive. The file will be extracted and used as the index page.</p> <p><i>See Adding Files to the Installer for more information.</i></p>
Example	<code>action.customindexpage=resources/index.html</code>

Header Type

Property	<code>action.config.headertype</code>
Value	The header type to use. Should be <code>STANDARD</code> , <code>CUSTOM</code> or <code>NONE</code> .
Default	<code>STANDARD</code>
Example	<code>action.config.headertype=NONE</code>

Standard Header URL

Property	<code>action.config.standardheaderurl</code>
Value	Override the header used when the header type is <code>STANDARD</code> . This may be an absolute or relative URL.
Example	<code>action.config.standardheaderurl=header.html</code>

Custom Header URL

Property	<code>action.config.customheaderurl</code>
Value	The URL used when the header type is <code>CUSTOM</code> . This may be an absolute or relative URL.
Example	<code>action.config.customheaderurl=header.html</code>

Footer Type

Property	<code>action.config.footertype</code>
Value	The footer type to use. Should be <code>STANDARD</code> , <code>CUSTOM</code> or <code>NONE</code> .
Default	<code>STANDARD</code>
Example	<code>action.config.footertype=NONE</code>

Standard Footer URL

Property	<code>action.config.standardfooterurl</code>
Value	Override the footer used when the footer type is <code>STANDARD</code> . This may be an absolute or relative URL.
Example	<code>action.config.standardfooterurl=footer.html</code>

Custom Footer URL

Property	<code>action.config.customfooterurl</code>
Value	The URL used when the footer type is <code>CUSTOM</code> . This may be an absolute or relative URL.
Example	<code>action.config.customfooterurl=footer.html</code>

[top](#)

Best Practice Tips

When running terminal commands, be vary of values using special characters. For instance, if your password contains a special character such as a double quote or an asterisk, then you must escape the character by using the backslash character right before it. So if your password is regional"5^, then you must type in regional\"5^.

This is especially important for 'reserved' characters (i.e. characters that have a special meaning in the command terminal, such as `<`, `>`, `@`, `|`, `&`, `"`, and more) and practices that pass values in double quotes. In case of the quotes, the system will assume that the mid-password quote is the closing quote, thereby ignoring the remaining value.