

# Yellowfin Configuration

- [Overview](#)
- [General System Settings](#)
  - [Java Path](#)
  - [Application Name](#)
  - [Application .war File Name](#)
  - [Application Log File Name](#)
  - [Base Tags Option](#)
  - [Date Format](#)
  - [Export Filename](#)
  - [Support Email Address](#)
  - [Use UserId Authentication](#)
  - [Adding Additional Files](#)
- [Administrator User](#)
  - [Administrator Username](#)
  - [Administrator User Password](#)
  - [Administrator User First Name](#)
  - [Administrator User Last Name](#)
  - [Administrator User Email Address](#)
- [LDAP Settings](#)
  - [LDAP Bind Username](#)
  - [LDAP Bind Password](#)
- [Broadcast Email](#)
  - [Broadcast Email Address](#)
  - [Broadcast Email Name](#)
- [SMTP Server](#)
  - [SMTP Server Hostname](#)
  - [SMTP Server Port](#)
  - [SMTP Server SSL Option](#)
  - [SMTP Server StartTLS Option](#)
  - [SMTP Server Authentication](#)
  - [SMTP Server Username](#)
  - [SMTP Server Password](#)
- [Dashboard Settings](#)
  - [Dashboard Width](#)
  - [Dashboard Associated Reports Location](#)
  - [Dashboard Analytic Filter Location](#)
  - [Dashboard Search Location](#)
- [Navigation Settings](#)
  - [Show Toolbar](#)
  - [Show Logoff Link on Toolbar](#)
- [Integration Settings](#)
  - [Custom Index Page](#)
  - [Header Type](#)
  - [Standard Header URL](#)
  - [Custom Header URL](#)
  - [Footer Type](#)
  - [Standard Footer URL](#)
  - [Custom Footer URL](#)

## Overview

[top](#)

These properties modify the default configuration of the Yellowfin installation, post-install.

## General System Settings

[top](#)

### Java Path

|          |                                                                                                                                                               |
|----------|---------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Property | option.javahome                                                                                                                                               |
| Value    | The location of the java installation that should be used to run Yellowfin. If this is not set, the java installation used to run the installer will be used. |
| Example  | option.javahome=/usr/lib/jvm/java-6-sun                                                                                                                       |

### Application Name

|                 |                                                                                        |
|-----------------|----------------------------------------------------------------------------------------|
| <b>Property</b> | action.config.appname                                                                  |
| <b>Value</b>    | The application name that is displayed within the application, instead of “Yellowfin”. |
| <b>Default</b>  | Yellowfin                                                                              |
| <b>Example</b>  | action.config.appname=BI Blue                                                          |

## Application .war File Name

|                 |                                                      |
|-----------------|------------------------------------------------------|
| <b>Property</b> | installer.warfilename                                |
| <b>Value</b>    | The name of the web application archive (.war) file. |
| <b>Default</b>  | yellowfin.war                                        |
| <b>Example</b>  | installer.warfilename=reports.war                    |

## Application Log File Name

|                 |                                                                                            |
|-----------------|--------------------------------------------------------------------------------------------|
| <b>Property</b> | installer.applogfilename                                                                   |
| <b>Value</b>    | The name of the application log file. Yellowfin logs to this file during normal operation. |
| <b>Default</b>  | yellowfin.log                                                                              |
| <b>Example</b>  | installer.applogfilename=reports.log                                                       |

## Base Tags Option

|                 |                                                                                                   |
|-----------------|---------------------------------------------------------------------------------------------------|
| <b>Property</b> | action.config.basetags                                                                            |
| <b>Value</b>    | Whether <base> tags should be included in html within the Yellowfin. Should be YES, NO or COMMENT |
| <b>Default</b>  | COMMENT                                                                                           |
| <b>Example</b>  | action.config.basetags=NO                                                                         |

## Date Format

|                 |                                                     |
|-----------------|-----------------------------------------------------|
| <b>Property</b> | action.config.dateformat                            |
| <b>Value</b>    | The default date format. Should be DMY, MDY or YMD. |
| <b>Default</b>  | DMY                                                 |
| <b>Example</b>  | action.config.dateformat=MDY                        |

## Export Filename

|                 |                                            |
|-----------------|--------------------------------------------|
| <b>Property</b> | action.config.exportfilename               |
| <b>Value</b>    | The filename used for XML content exports. |
| <b>Default</b>  | YellowfinExport.xml                        |
| <b>Example</b>  | action.config.exportfilename=BIExport.xml  |

## Support Email Address

|                 |                                                                       |
|-----------------|-----------------------------------------------------------------------|
| <b>Property</b> | <code>action.config.supportemail</code>                               |
| <b>Value</b>    | The support email address. Error reports can be sent to this address. |
| <b>Default</b>  | <code>support@yellowfin.com.au</code>                                 |
| <b>Example</b>  | <code>action.config.supportemail=support@example.com</code>           |

## Use UserId Authentication

|                 |                                                                                  |
|-----------------|----------------------------------------------------------------------------------|
| <b>Property</b> | <code>action.authentication.userid</code>                                        |
| <b>Value</b>    | If this is set to true, users log in with a UserId rather than an email address. |
| <b>Default</b>  | <code>false</code>                                                               |
| <b>Example</b>  | <code>action.authentication.userid=true</code>                                   |

## Adding Additional Files

See [Adding Files to the Application](#) for more information.

## Administrator User

[top](#)

### Administrator Username

|                 |                                                                |
|-----------------|----------------------------------------------------------------|
| <b>Property</b> | <code>action.adminuser.username</code>                         |
| <b>Value</b>    | The login username for the initial administrator user account. |
| <b>Default</b>  | <code>admin@yellowfin.com.au</code>                            |
| <b>Example</b>  | <code>action.adminuser.username=adminuser</code>               |

### Administrator User Password

|                 |                                                          |
|-----------------|----------------------------------------------------------|
| <b>Property</b> | <code>action.adminuser.password</code>                   |
| <b>Value</b>    | The password for the initial administrator user account. |
| <b>Default</b>  | <code>test</code>                                        |
| <b>Example</b>  | <code>action.adminuser.password=secret</code>            |

### Administrator User First Name

|                 |                                                            |
|-----------------|------------------------------------------------------------|
| <b>Property</b> | <code>action.adminuser.firstname</code>                    |
| <b>Value</b>    | The first name for the initial administrator user account. |
| <b>Default</b>  | <code>System</code>                                        |
| <b>Example</b>  | <code>action.adminuser.firstname=Joe</code>                |

### Administrator User Last Name

|                 |                                        |
|-----------------|----------------------------------------|
| <b>Property</b> | <code>action.adminuser.lastname</code> |
|-----------------|----------------------------------------|

|                |                                                           |
|----------------|-----------------------------------------------------------|
| <b>Value</b>   | The last name for the initial administrator user account. |
| <b>Default</b> | Administrator                                             |
| <b>Example</b> | action.adminuser.lastname=Smith                           |

## Administrator User Email Address

|                 |                                                               |
|-----------------|---------------------------------------------------------------|
| <b>Property</b> | action.adminuser.email                                        |
| <b>Value</b>    | The email address for the initial administrator user account. |
| <b>Default</b>  | admin@yellowfin.com.au                                        |
| <b>Example</b>  | action.adminuser.lastname=admin@example.com                   |

## LDAP Settings

[top](#)

### LDAP Bind Username

|                 |                                     |
|-----------------|-------------------------------------|
| <b>Property</b> | action.config.ldapbinduser          |
| <b>Value</b>    | The default LDAP bind username.     |
| <b>Example</b>  | action.config.ldapbinduser=username |

### LDAP Bind Password

|                 |                                       |
|-----------------|---------------------------------------|
| <b>Property</b> | action.config.ldapbindpassword        |
| <b>Value</b>    | The default LDAP bind password.       |
| <b>Example</b>  | action.config.ldapbindpassword=secret |

## Broadcast Email

[top](#)

### Broadcast Email Address

|                 |                                                            |
|-----------------|------------------------------------------------------------|
| <b>Property</b> | action.config.broadcastemail                               |
| <b>Value</b>    | The email address that broadcast emails will be sent from. |
| <b>Default</b>  | no-reply@yellowfin.com.au                                  |
| <b>Example</b>  | action.config.broadcastemail=reports@example.com           |

### Broadcast Email Name

|                 |                                             |
|-----------------|---------------------------------------------|
| <b>Property</b> | action.config.broadcastname                 |
| <b>Value</b>    | The from name for broadcast emails.         |
| <b>Default</b>  | Yellowfin Reports                           |
| <b>Example</b>  | action.config.broadcastname=BI Blue Reports |

## SMTP Server

[top](#)

### SMTP Server Hostname

|          |                                                       |
|----------|-------------------------------------------------------|
| Property | action.config.smtpserver                              |
| Value    | The hostname of the smtp server to send mail through. |
| Example  | action.config.smtpserver=mail.example.com             |

### SMTP Server Port

|          |                            |
|----------|----------------------------|
| Property | action.config.smtpport     |
| Value    | The smtp server port.      |
| Example  | action.config.smtpport=465 |

### SMTP Server SSL Option

|          |                                                                 |
|----------|-----------------------------------------------------------------|
| Property | action.config.smtpssl                                           |
| Value    | Set this to true to use SSL when connecting to the SMTP server. |
| Default  | false                                                           |
| Example  | action.config.smtpssl=true                                      |

### SMTP Server StartTLS Option

|          |                                                                                  |
|----------|----------------------------------------------------------------------------------|
| Property | action.config.smtpstarttls                                                       |
| Value    | Set this to true to use the StartTLS command when connecting to the SMTP server. |
| Default  | false                                                                            |
| Example  | action.config.smtpstarttls=true                                                  |

### SMTP Server Authentication

|          |                                                                            |
|----------|----------------------------------------------------------------------------|
| Property | action.config.smtpauth                                                     |
| Value    | Set this to true to use authentication when connecting to the SMTP server. |
| Default  | false                                                                      |
| Example  | action.config.smtpauth=true                                                |

### SMTP Server Username

|          |                                                             |
|----------|-------------------------------------------------------------|
| Property | action.config.smtpusername                                  |
| Value    | The username used when authenticating with the SMTP server. |
| Example  | action.config.smtpusername=username                         |

### SMTP Server Password

|                 |                                                             |
|-----------------|-------------------------------------------------------------|
| <b>Property</b> | <code>action.config.smtppassword</code>                     |
| <b>Value</b>    | The password used when authenticating with the SMTP server. |
| <b>Example</b>  | <code>action.config.smtppassword=secret</code>              |

## Dashboard Settings

[top](#)

### Dashboard Width

|                 |                                          |
|-----------------|------------------------------------------|
| <b>Property</b> | <code>action.config.dashwidth</code>     |
| <b>Value</b>    | The default dashboard width in pixels.   |
| <b>Default</b>  | 1000                                     |
| <b>Example</b>  | <code>action.config.dashwidth=800</code> |

### Dashboard Associated Reports Location

|                 |                                                                           |
|-----------------|---------------------------------------------------------------------------|
| <b>Property</b> | <code>action.config.associatedreports</code>                              |
| <b>Value</b>    | The position of associated reports on dashboards. Should be RIGHT or OFF. |
| <b>Default</b>  | RIGHT                                                                     |
| <b>Example</b>  | <code>action.config.associatedreports=OFF</code>                          |

### Dashboard Analytic Filter Location

|                 |                                                                                  |
|-----------------|----------------------------------------------------------------------------------|
| <b>Property</b> | <code>action.config.dashanalyticfilters</code>                                   |
| <b>Value</b>    | The default position of analytic filters on dashboards. Should be LEFT or RIGHT. |
| <b>Example</b>  | <code>action.config.dashanalyticfilters=RIGHT</code>                             |

### Dashboard Search Location

|                 |                                                                                    |
|-----------------|------------------------------------------------------------------------------------|
| <b>Property</b> | <code>action.config.searchlocation</code>                                          |
| <b>Value</b>    | The position of the search box on the dashboard page. Should be TOP, RIGHT or OFF. |
| <b>Default</b>  | TOP                                                                                |
| <b>Example</b>  | <code>action.config.searchlocation=RIGHT</code>                                    |

## Navigation Settings

[top](#)

### Show Toolbar

|                 |                                                               |
|-----------------|---------------------------------------------------------------|
| <b>Property</b> | <code>action.config.showtoolbar</code>                        |
| <b>Value</b>    | Set to false to disable the application toolbar on all pages. |
| <b>Default</b>  | true                                                          |

|                |                                              |
|----------------|----------------------------------------------|
| <b>Example</b> | <code>action.config.showtoolbar=false</code> |
|----------------|----------------------------------------------|

## Show Logoff Link on Toolbar

|                 |                                                                     |
|-----------------|---------------------------------------------------------------------|
| <b>Property</b> | <code>action.config.showtoolbarlogoff</code>                        |
| <b>Value</b>    | Set to false to disable the logoff link on the application toolbar. |
| <b>Default</b>  | true                                                                |
| <b>Example</b>  | <code>action.config.showtoolbarlogoff=false</code>                  |

## Integration Settings

[top](#)

## Custom Index Page

|                 |                                                                                                                                                                                                                                                                                 |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Property</b> | <code>action.customindexpage</code>                                                                                                                                                                                                                                             |
| <b>Value</b>    | The location of a custom index page. This property points to a resource within the installer archive. The file will be extracted and used as the index page.<br><br><div> <div></div> <div>See <a href="#">Adding Files to the Installer</a> for more information.</div> </div> |
| <b>Example</b>  | <code>action.customindexpage=resources/index.html</code>                                                                                                                                                                                                                        |

## Header Type

|                 |                                                             |
|-----------------|-------------------------------------------------------------|
| <b>Property</b> | <code>action.config.headertype</code>                       |
| <b>Value</b>    | The header type to use. Should be STANDARD, CUSTOM or NONE. |
| <b>Default</b>  | STANDARD                                                    |
| <b>Example</b>  | <code>action.config.headertype=NONE</code>                  |

## Standard Header URL

|                 |                                                                                                     |
|-----------------|-----------------------------------------------------------------------------------------------------|
| <b>Property</b> | <code>action.config.standardheaderurl</code>                                                        |
| <b>Value</b>    | Override the header used when the header type is STANDARD. This may be an absolute or relative URL. |
| <b>Example</b>  | <code>action.config.standardheaderurl=header.html</code>                                            |

## Custom Header URL

|                 |                                                                                       |
|-----------------|---------------------------------------------------------------------------------------|
| <b>Property</b> | <code>action.config.customheaderurl</code>                                            |
| <b>Value</b>    | The URL used when the header type is CUSTOM. This may be an absolute or relative URL. |
| <b>Example</b>  | <code>action.config.customheaderurl=header.html</code>                                |

## Footer Type

|                 |                                                             |
|-----------------|-------------------------------------------------------------|
| <b>Property</b> | <code>action.config.footertype</code>                       |
| <b>Value</b>    | The footer type to use. Should be STANDARD, CUSTOM or NONE. |

|                |                                            |
|----------------|--------------------------------------------|
| <b>Default</b> | STANDARD                                   |
| <b>Example</b> | <code>action.config.footertype=NONE</code> |

## Standard Footer URL

|                 |                                                                                                     |
|-----------------|-----------------------------------------------------------------------------------------------------|
| <b>Property</b> | <code>action.config.standardfooterurl</code>                                                        |
| <b>Value</b>    | Override the footer used when the footer type is STANDARD. This may be an absolute or relative URL. |
| <b>Example</b>  | <code>action.config.standardfooterurl=footer.html</code>                                            |

## Custom Footer URL

|                 |                                                                                       |
|-----------------|---------------------------------------------------------------------------------------|
| <b>Property</b> | <code>action.config.customfooterurl</code>                                            |
| <b>Value</b>    | The URL used when the footer type is CUSTOM. This may be an absolute or relative URL. |
| <b>Example</b>  | <code>action.config.customfooterurl=footer.html</code>                                |

[top](#)