

Yellowfin Configuration

- [Overview](#)
- [General System Settings](#)
 - [Java Path](#)
 - [Application Name](#)
 - [Application .war File Name](#)
 - [Application Log File Name](#)
 - [Base Tags Option](#)
 - [Date Format](#)
 - [Export Filename](#)
 - [Support Email Address](#)
 - [Use UserId Authentication](#)
 - [Adding Additional Files](#)
- [Administrator User](#)
 - [Administrator Username](#)
 - [Administrator User Password](#)
 - [Administrator User First Name](#)
 - [Administrator User Last Name](#)
 - [Administrator User Email Address](#)
- [LDAP Settings](#)
 - [LDAP Bind Username](#)
 - [LDAP Bind Password](#)
- [Broadcast Email](#)
 - [Broadcast Email Address](#)
 - [Broadcast Email Name](#)
- [SMTP Server](#)
 - [SMTP Server Hostname](#)
 - [SMTP Server Port](#)
 - [SMTP Server SSL Option](#)
 - [SMTP Server StartTLS Option](#)
 - [SMTP Server Authentication](#)
 - [SMTP Server Username](#)
 - [SMTP Server Password](#)
- [Dashboard Settings](#)
 - [Dashboard Width](#)
 - [Dashboard Associated Reports Location](#)
 - [Dashboard Analytic Filter Location](#)
 - [Dashboard Search Location](#)
- [Navigation Settings](#)
 - [Show Toolbar](#)
 - [Show Logoff Link on Toolbar](#)
- [Integration Settings](#)
 - [Custom Index Page](#)
 - [Header Type](#)
 - [Standard Header URL](#)
 - [Custom Header URL](#)
 - [Footer Type](#)
 - [Standard Footer URL](#)
 - [Custom Footer URL](#)

Overview

[top](#)

These properties modify the default configuration of the Yellowfin installation, post-install.

General System Settings

[top](#)

Java Path

Property	<code>option.javahome</code>
Value	The location of the java installation that should be used to run Yellowfin. If this is not set, the java installation used to run the installer will be used.
Example	<code>option.javahome=/usr/lib/jvm/java-6-sun</code>

Application Name

Property	action.config.appname
Value	The application name that is displayed within the application, instead of “Yellowfin”.
Default	Yellowfin
Example	action.config.appname=BI Blue

Application .war File Name

Property	installer.warfilename
Value	The name of the web application archive (.war) file.
Default	yellowfin.war
Example	installer.warfilename=reports.war

Application Log File Name

Property	installer.applogfilename
Value	The name of the application log file. Yellowfin logs to this file during normal operation.
Default	yellowfin.log
Example	installer.applogfilename=reports.log

Base Tags Option

Property	action.config.basetags
Value	Whether <base> tags should be included in html within the Yellowfin. Should be YES, NO or COMMENT
Default	COMMENT
Example	action.config.basetags=NO

Date Format

Property	action.config.dateformat
Value	The default date format. Should be DMY, MDY or YMD.
Default	DMY
Example	action.config.dateformat=MDY

Export Filename

Property	action.config.exportfilename
Value	The filename used for XML content exports.
Default	YellowfinExport.xml
Example	action.config.exportfilename=BIExport.xml

Support Email Address

Property	<code>action.config.supportemail</code>
Value	The support email address. Error reports can be sent to this address.
Default	<code>support@yellowfin.com.au</code>
Example	<code>action.config.supportemail=support@example.com</code>

Use UserId Authentication

Property	<code>action.authentication.userid</code>
Value	If this is set to true, users log in with a UserId rather than an email address.
Default	<code>false</code>
Example	<code>action.authentication.userid=true</code>

Adding Additional Files

See [Adding Files to the Application](#) for more information.

Administrator User

[top](#)

Administrator Username

Property	<code>action.adminuser.username</code>
Value	The login username for the initial administrator user account.
Default	<code>admin@yellowfin.com.au</code>
Example	<code>action.adminuser.username=adminuser</code>

Administrator User Password

Property	<code>action.adminuser.password</code>
Value	The password for the initial administrator user account.
Default	<code>test</code>
Example	<code>action.adminuser.password=secret</code>

Administrator User First Name

Property	<code>action.adminuser.firstname</code>
Value	The first name for the initial administrator user account.
Default	<code>System</code>
Example	<code>action.adminuser.firstname=Joe</code>

Administrator User Last Name

Property	<code>action.adminuser.lastname</code>
-----------------	--

Value	The last name for the initial administrator user account.
Default	Administrator
Example	action.adminuser.lastname=Smith

Administrator User Email Address

Property	action.adminuser.email
Value	The email address for the initial administrator user account.
Default	admin@yellowfin.com.au
Example	action.adminuser.lastname=admin@example.com

LDAP Settings

[top](#)

LDAP Bind Username

Property	action.config.ldapbinduser
Value	The default LDAP bind username.
Example	action.config.ldapbinduser=username

LDAP Bind Password

Property	action.config.ldapbindpassword
Value	The default LDAP bind password.
Example	action.config.ldapbindpassword=secret

Broadcast Email

[top](#)

Broadcast Email Address

Property	action.config.broadcastemail
Value	The email address that broadcast emails will be sent from.
Default	no-reply@yellowfin.com.au
Example	action.config.broadcastemail=reports@example.com

Broadcast Email Name

Property	action.config.broadcastname
Value	The from name for broadcast emails.
Default	Yellowfin Reports
Example	action.config.broadcastname=BI Blue Reports

SMTP Server

[top](#)

SMTP Server Hostname

Property	action.config.smtpserver
Value	The hostname of the smtp server to send mail through.
Example	action.config.smtpserver=mail.example.com

SMTP Server Port

Property	action.config.smtpport
Value	The smtp server port.
Example	action.config.smtpport=465

SMTP Server SSL Option

Property	action.config.smtpssl
Value	Set this to true to use SSL when connecting to the SMTP server.
Default	false
Example	action.config.smtpssl=true

SMTP Server StartTLS Option

Property	action.config.smtpstarttls
Value	Set this to true to use the StartTLS command when connecting to the SMTP server.
Default	false
Example	action.config.smtpstarttls=true

SMTP Server Authentication

Property	action.config.smtpauth
Value	Set this to true to use authentication when connecting to the SMTP server.
Default	false
Example	action.config.smtpauth=true

SMTP Server Username

Property	action.config.smtpusername
Value	The username used when authenticating with the SMTP server.
Example	action.config.smtpusername=username

SMTP Server Password

Property	<code>action.config.smtppassword</code>
Value	The password used when authenticating with the SMTP server.
Example	<code>action.config.smtppassword=secret</code>

Dashboard Settings

[top](#)

Dashboard Width

Property	<code>action.config.dashwidth</code>
Value	The default dashboard width in pixels.
Default	1000
Example	<code>action.config.dashwidth=800</code>

Dashboard Associated Reports Location

Property	<code>action.config.associatedreports</code>
Value	The position of associated reports on dashboards. Should be RIGHT or OFF.
Default	RIGHT
Example	<code>action.config.associatedreports=OFF</code>

Dashboard Analytic Filter Location

Property	<code>action.config.dashanalyticfilters</code>
Value	The default position of analytic filters on dashboards. Should be LEFT or RIGHT.
Example	<code>action.config.dashanalyticfilters=RIGHT</code>

Dashboard Search Location

Property	<code>action.config.searchlocation</code>
Value	The position of the search box on the dashboard page. Should be TOP, RIGHT or OFF.
Default	TOP
Example	<code>action.config.searchlocation=RIGHT</code>

Navigation Settings

[top](#)

Show Toolbar

Property	<code>action.config.showtoolbar</code>
Value	Set to false to disable the application toolbar on all pages.
Default	true

Example	<code>action.config.showtoolbar=false</code>
----------------	--

Show Logoff Link on Toolbar

Property	<code>action.config.showtoolbarlogoff</code>
Value	Set to false to disable the logoff link on the application toolbar.
Default	true
Example	<code>action.config.showtoolbarlogoff=false</code>

Integration Settings

[top](#)

Custom Index Page

Property	<code>action.customindexpage</code>
Value	The location of a custom index page. This property points to a resource within the installer archive. The file will be extracted and used as the index page. See Adding Files to the Installer for more information.
Example	<code>action.customindexpage=resources/index.html</code>

Header Type

Property	<code>action.config.headertype</code>
Value	The header type to use. Should be STANDARD, CUSTOM or NONE.
Default	STANDARD
Example	<code>action.config.headertype=NONE</code>

Standard Header URL

Property	<code>action.config.standardheaderurl</code>
Value	Override the header used when the header type is STANDARD. This may be an absolute or relative URL.
Example	<code>action.config.standardheaderurl=header.html</code>

Custom Header URL

Property	<code>action.config.customheaderurl</code>
Value	The URL used when the header type is CUSTOM. This may be an absolute or relative URL.
Example	<code>action.config.customheaderurl=header.html</code>

Footer Type

Property	<code>action.config.footertype</code>
Value	The footer type to use. Should be STANDARD, CUSTOM or NONE.

Default	STANDARD
Example	<code>action.config.footertype=NONE</code>

Standard Footer URL

Property	<code>action.config.standardfooterurl</code>
Value	Override the footer used when the footer type is STANDARD. This may be an absolute or relative URL.
Example	<code>action.config.standardfooterurl=footer.html</code>

Custom Footer URL

Property	<code>action.config.customfooterurl</code>
Value	The URL used when the footer type is CUSTOM. This may be an absolute or relative URL.
Example	<code>action.config.customfooterurl=footer.html</code>

[top](#)