

Initial Setup

- [Overview](#)
- [Activating Client Org functionality](#)
 - [Enable client organizations](#)
 - [Check role permissions are enabled](#)
- [Creating client organizations](#)
 - [Client Reference ID](#)
 - [Users](#)
 - [Groups](#)
- [Access to client orgs](#)
 - [Securing Primary Org Content](#)
- [Group visibility between orgs](#)
- [Configuration Options](#)
 - [Displaying current client organization](#)

Overview

[Initial Setup#top](#)

The Client Organization structure is disabled by default. It can be switched on from the Administration area of Yellowfin. There are currently two options that can be enabled.

Option name	Option description
Client Organization Functionality	This enables the Client Organizations features of Yellowfin. If it is not enabled, Yellowfin ignores this functionality altogether.
Global Annotations	This option is only displayed when Client Organization Functionality is enabled. Annotations on reports are normally only shared with other members of a single organization, even if a report is visible to members of other organizations. Enabling Global Annotations here means shared reports also have annotations attached to them shared. Learn more about annotations .


Activating Client Org functionality

To start using client organizations, enable the feature via the Administration area of Yellowfin, then check that role permissions are enabled for any users who might need to manage client orgs.


Enable client organizations

Anyone with Yellowfin administrator rights can enable client orgs. Follow the steps below.

1. On the left-side navigation pane, click on **Administration**, then **Configuration**.
2. Click on the **Authentication**  tool along the top of the screen, then click on the **Client Organizations** section to display the following options:



3. Click on the toggle for **Client Organization Functionality**. Also choose whether you'd like to enable global annotations via the **Global Annotations** toggle (see table above for more info).




Check role permissions are enabled

A system administrator would typically manage client orgs, so end-users usually don't need this functionality. However, you can assign options to different roles, including access to create ("C") new client organizations, view ("R") existing client orgs, update ("U") the details of existing client orgs and delete ("D") any client orgs.

To check or enable the required role permission to manage client orgs, follow these steps.

1. On the left-side navigation pane, click on **Administration**, then **Admin Console**.
2. Click on the **Roles** section and select the role you wish to grant access to, which will open the Role Management page.



3. Scroll down to the **Administration** section and click on it to expand the role permissions.
4. Check the box for **Client Organization Management**, then check any required permissions (C, R U and/or D, described above).



5. Scroll up or down to the **Save** button and click on it to save your changes.



If the changes apply to the role you're currently logged into Yellowfin with, you will need to log out and back in again for the changes to take effect.

Creating client organizations

Initial Setup#top

Once you've enabled client orgs, you can create individual client orgs with their own time zone, style, name and more. Before you begin, there are several fields to define.

Client Reference ID

A client org is identified by a **Client Reference ID**. This is an arbitrary text identifier of characters, numbers or both, assigned when the client org is created. This ID must uniquely identify the org across the entire system and may not be left blank. The Default Org is an exception to this, as the ID is initially blank, but can be defined at any time.

Generally, the Client Reference ID should be an internal, unique code that you use to identify a client. Yellowfin can use this code to filter reports based on which client a user has logged into. A display name for the client is also set, which may be different to the ID.

Users

A user must first be created in the system before they can be added to a client org. They can be created either at the primary org or client org level. When a new user is created, they are automatically assigned access to the organization they were created in. If users were created before client orgs were enabled, they will need to be manually added to any client orgs they require access to. Once created in Yellowfin, users can be assigned access to any org (primary or client) in the system.


Groups

By default, user groups can only contain users who have login access to the client org containing the group. For example, if an administrator creates a group for Client 1, only users of Client 1 can be added to the Group, Client 2 Users will not.


However, groups can also be set to be visible across all organizations in an instance. In this case, if an administrator creates a group for Client 1 and sets it to be visible at client organizations, users of both Client 1 and Client 2 can be added to the group. For further details...

When you are ready to create a new client org, follow the steps below.

1. On the left-side navigation pane, click on **Administration**, then **Client Organizations** to display the Client Organizations page.



The Client Organizations page will appear:



2. Click on the **Add** button, which will open another new window:

Client Organization

Name: ⓘ

Client Reference Id: ⓘ

Time Zone: ▼ ⓘ

▼ ⓘ

Custom style path:

This path is used for custom styles specific to this client organization.
Custom CSS files should be placed in the directory:
customcss/
Custom image files should be placed in the directory:
customimages/

Users

ⓘ Users added to this list are allowed to log on to this Client Organization.

Name	Role
None Found	

3. In the **Name** field, type the display name for the client organization.
4. In the **Client Reference ID** field, type used to uniquely identify the client org. This can be characters, numbers or a mix of both. Use whatever works best for your environment.
5. In the **Time Zone** field, set the correct time zone according to GMT. This is used as the default time zone when new data sources and users are created within this client org.
6. In the **Custom Style Path** field, you can provide a path to a custom style sheet for this client org. This field is not mandatory.

Client Organization

Name: ⓘ

Client Reference Id: ⓘ

Time Zone: ▼ ⓘ

▼ ⓘ

Custom style path:

This path is used for custom styles specific to this client organization.
Custom CSS files should be placed in the directory:
customcss/
Custom image files should be placed in the directory:
customimages/

7. Click on the **Add** button to add any exiting users who should have access to this client org.

Users

 Users added to this list are allowed to log on to this Client Organization.

Add

	Name	Role
<input type="checkbox"/>	System Administrator	System Administrator
<input type="checkbox"/>	Rafe Carson	Consumer & Collaborator
<input type="checkbox"/>	April Hollands	Public Content Writer & Collaborator - Advanced
<input type="checkbox"/>	Zoe Ortiz	System Administrator
<input type="checkbox"/>	Naveen Patel	Public Content Writer & Collaborator - Advanced
<input type="checkbox"/>	Jo Pickett	Personal Content Writer & Collaborator
<input type="checkbox"/>	Hazel Salinas	Public Content Writer & Collaborator

Remove

Save **Cancel**

8. Click on the **Save** button to save the new client org details.

Access to client orgs

Initial Setup#top

A user may only ever log into one organization at a time, even if they can access more than one organization. As part of the login process, Yellowfin checks which orgs the user can access. If they have access to a single org, they will automatically be logged into that org. If, however, they have access to multiple orgs, they will be prompted to select an which organization they would like to access:

Multi-tenant Login

You have access to multiple client organisations.
Please select the client you wish to log into.

- Default
- Dragonfly[DF]

Login



Note

If you wish to specify which org the user logs into, this selection screen can be bypassed using a custom login page, or with web services.

Content visibility between orgs

[Initial Setup#top](#)

Content created at the primary organization is shared to all clients, so a user logging into a particular client will be able to see any content created at that client, as well as any content created at the primary organization.

See [Content Management](#) for more information.

Securing Primary Org Content

It is possible to assign access permissions to content located in the primary org by securing the Content Categories it's stored in, based on Client Org User Groups.

See [Primary Org Content Security](#) for more information.

Group visibility between orgs

From Yellowfin 9.4, groups can be set to be visible to more than just one organization, if desired. If you choose to enable this option, client org privacy is enforced. For example, users from one organization will not be able to see users in the same group from any another organization.

See [User Groups](#) for more detailed information.

Configuration Options

[Initial Setup#top](#)

The **Configuration** and **Report Styles** pages in Administration allow Yellowfin administrators to set options that affect functionality, system parameters, and default style settings per organization. When a client organization is created, all of these settings are copied from the primary organization. An administrator can then log in to the client org and customize the settings for the client. This allows each client to have different regional settings, integration options, and styles.




Note

Some configuration options are only applicable to the primary organization, and will not be shown when logged in to a client.

Any changes to primary organization configuration may be optionally applied to any client organizations. Below are the steps to control this functionality, presuming you're an admin of the primary org with the typical default access to manage client orgs.

1. Make a change to any of the primary org config options. In this example, we added a language.

2. Click on the **Save** button to save your changes.
Before the configuration update is save, you'll be prompted to select whether you wish to apply the update to client orgs:






Save Configuration Settings

The following configuration settings have been changed:
ISO language

Should these changes be applied to client organizations as well?

No Yes

3. Click on the **Yes** radio button.
A further prompt will appear, asking you to choose which client orgs to apply the changes to:





Save Configuration Settings

The following configuration settings have been changed:
ISO language

Should these changes be applied to client organizations as well?

No Yes

Please select the client organizations from the list below to have changes applied.

BFA Ltd
 Dragonfly

[Select All](#) [Select None](#)

4. Click on any client orgs you wish to include in the configuration change, then click on the **Save** button.

Displaying current client organization

For users who access more than one client org and routinely move between different client organizations, it may be useful to display which client a user is currently logged in to. To enable this display, follow the instructions below.

1. On the left-side navigation pane, click on **Administration**, then **Configuration**.
2. Click on the **Integration** button, then click on the **Page Header** section to expand it.

3. Click on the toggle for **Client** to enabled it, then **save** the changes. There are also options to display the name and role of the current user:

Page Header ^

Display Standard
Display the standard Yellowfin branded header at the top of the page throughout the system. Custom
None


Page Title
Hide the page title from the header area of the page.

User
Display the name of the current user in the header area of the page.

Client
Display the name of the current client org in the header area of the page.

Role
Display the name of the current user's role in the header area of the page.

Using the example above, the following items would be displayed in the standard Yellowfin header:



[Initial Setup#top](#)