

# Steps & Connections

- Overview
  - Steps
    - Input Steps
    - Transformation Steps
    - Output Steps
    - Step Functions
  - Connections
    - Creating a Connection
    - Connection Rules
    - Connection Functions
    - Breaking a Connection
    - Editing a Connection Flow

## Overview

Transformation flows are created by combining various steps through connections. Use the information below to learn more about these steps and connections.

## Steps

There are three types of steps that can be included in a transformation flow.

### Input Steps


Include an input step to define where to extract your data from. The following types can be used:

↑

↓

Input Steps

✕




API

↑

Extract from Single Third Party Ta...


This step is for extracting data from a single third party table



SQL


Extract from Freehand SQL

This step is for extracting by using Freehand SQL




Extract from Single Table

This step is for extracting from a single database table





Extract from Delimited File



This step is for extracting from a delimited file



Extract from Report

This step is for extracting from a Report

Icon	Input Step	Description
	Third-party Connector	To extract data from a single third-party connection table. The connectors currently supported are: Google Analytics, Google Sheets, and Salesforce.
SQL	Freehand SQL	Use this method to import data from a database using an SQL query.
	Single table	This input step can be used to import data from a single database table.








	Delimited file	This input method is used when extracting data from a delimited file (that is, a file with separators).
	Report	Use this method to use a Yellowfin report as the source of data. This method accepts 2-dimensional reports, but not multi-dimensional ones. The following types of reports are currently not supported: Jasper, SSRS, and BIRT.






Click [here](#) to learn more about these steps and how to configure them.


[top](#)

## Transformation Steps

Use a transformation step to transform or convert the connected data. Yellowfin includes the following built-in transformations, however more can be added.

Transformation Steps		
		<b>Aggregate</b> This step provides aggregates of incoming data
		<b>Calculated Field</b> This step creates a calculated field from a calculation based on other...
		<b>Filter</b> This step is for filtering data in a step
		<b>Merge</b> This step merges two sets of data based on configured Join Fields
		<b>Split</b> This step duplicates an input dataset to create identical output datasets
		<b>Union</b> This step combines data from two inputs into one set which has rows...

Icon	Transformation type	Description
	Aggregate Step	This step transforms your data into a summary form, by applying functions like count, count distinct, sum, average, etc.
	Calculated Field	This step creates a calculated field based on other fields in the step.
	Filter	This step is for filtering data in a step.
	Merge	This step merges two sets of data based on the configured Join Fields.
	Split	This step duplicates an input dataset to create identical output datasets.


	Union	This step combines data from two datasets together into a singular field
---	-------	--


This [section](#) teaches you how to configure each of these steps, along with other types of transformations.

[top](#)

## Output Steps

Save the transformed data into a database using an output step.



Icon	Transformation type	Description
	SQL Database	This outputs data to a selected writeable data source. There are multiple options to create and manage tables and indexes, and to insert or update data.

Click [here](#) to learn how to configure this step.

[top](#)

## Step Functions

Once a step is added to the canvas, right-click on it to see the functions that can be performed on it.

Step
Copy
Run Step
Break connections
Delete

These are explained below:

Function	Description
Copy	To create a copy of the step.
Run Step	To execute only this step. Doing so will flood the Data Preview Panel with the step's data.
<a href="#">Break Connections</a>	To break any connections that the step has with other steps.
Delete	To delete the step.


[top](#)

## Connections


Connections are used to join steps together and create a relationship between them. Data will flow from one step to another step. Hover over a step to reveal its connecting points. These points are then used to connect one step to another. The flow of a connection is represented with an arrowhead at the end of it.

### Creating a Connection

1. Hover over a step. It's connecting points will become visible.
2. Then hover over one of these points until it turns orange.



3. Drag this point and drop it over another step that it needs to be connected to. A connection will be created between the steps.




### Connection Rules

These rules are applicable on connections (running left to right).

- An input step can be connected to only one transformation or output step.
- A transformation step cannot be connected to an input step, but to another transformation or output step.
- All types of transformation steps, except the split step, can only be connected to one other step.
- A split step can be connected multiple times.
- A merge step can accept multiple inputs.
- Connections can only be made to an output step, but it cannot be the origin of a connection.

### Connection Functions

Once a connection is created between steps, right-click on it to see the functions that can be performed.




These are explained below:


Function	Description
Edit Flow	To configure the mapping between the data fields in the connecting steps.
Break Connection	To delete the selected connection.

## Breaking a Connection

1. Once a connection is created between two steps, it can be broken or deleted. Simply right-click on the connection itself and select Break Connections.



2. Alternatively, right-click on one of the steps, and click on Break Connections. This will break all the connections associated with that step.
3. Confirmation will be required before the connection is deleted. Just click on the Confirm button to do so when the popup appears.



[top](#)


## Editing a Connection Flow

Connections allow for data to flow from one step to another. When they are established, data coming from the source step is automatically mapped to fields in the target step. However, with this option, you can change the mapping between the two steps. Any changes made to the flow will affect the target step and its subsequent steps; previous steps will not be affected.

**Note:** If data has already been mapped from one step to another, and then changed, it will need to be manually mapped again. For example, if data is extracted from a report and then connected to an aggregate step, but then the report fields get altered directly within the report, then the flow will have to be manually mapped to the new incoming fields.


1. Right-click on a connection to bring up the menu.

2. Click Edit Flow.



3. A popup will appear displaying the data mapped between the two steps. The incoming/source fields (from the previous step) will appear on the left side, and the target fields (for the next step) will appear on the right side.
4. You can perform the following types of actions on the mapping:
5. **Auto-mapping:** Allow Yellowfin to do the field mapping for you by clicking on the **Auto-Map Fields** button. The system automatically matches fields based on their names and data type. **Note:** This feature is ideal for situations in which a connection is deleted and then created again. The fields will not be mapped as before, and using this button will auto-map them correctly.
6. **Change mapping:** Hover your cursor over a field on the left side, and when the reorder icon appears, click and drag it to match any field on the right side.

Note: The target field will lose its previously mapped field, which will appear in the unmapped section.




7. **Deleting fields:** You can delete a field, in which case it will not be sent to the target step and any subsequent steps.

- a. Hover over a field on the right side, and when the delete icon appears, click on it.



- b. On doing so, the matched source field will be added to the unmapped section at the bottom.
- c. Delete this field from the unmapped section as well. It will not appear in the target step.

8. **Field unmapping:** If a field on the left side is deleted first, then the target field will lose its mapping. Similarly, fields can get unmapped when a mapping is changed or reordered. Unmapped fields will have the following warning appear next to them.



All target fields are required to be mapped, therefore you can either delete that target field, or drag another field to match with it. The removed field will be added to the unmapped section.

9. All **unmapped fields** appear at the bottom of the popup on the left side (as shown in the example below). Fields in the unmapped section will be sent to the target step, however any data conversions or field transformations previously made on them will be lost, and not be applied to these fields in the target and any subsequent steps. However, previous steps will not be affected.

The 'Map Steps' dialog box has a blue header with a close button. Below the header is a grey button labeled 'Auto-Map Fields'. The main area contains two columns of field names, each preceded by a vertical bar. The left column has a yellow bar for POSTCODE, a blue bar for LATITUDE, a blue bar for LONGITUDE, a yellow bar for GEOPOINT, a yellow bar for ISOCODE, a blue bar for ADDRESSID, a yellow bar for ADDRESSLINE1, a yellow bar for ADDRESSLINE2, and a yellow bar for ADDRESSLINE3. The right column has a yellow bar for POSTCODE, a blue bar for LATITUDE, a blue bar for LONGITUDE, a yellow bar for GEOPOINT, a yellow bar for ISOCODE, a blue bar for ADDRESSID, and is empty for the address lines. At the bottom is a large blue button labeled 'Done'.

10. Click on the Done button. A confirmation popup will appear, displaying mapping changes made to the flow.

The 'Map Steps' dialog box is shown with a grey background. A white error message box with a blue header and a yellow warning icon is overlaid in the center. The message reads: 'You must fix all errors before applying this field mapping'. Below the message is a blue button labeled 'Ok'. The background dialog box shows the same field mapping as in the previous screenshot, with the 'Done' button at the bottom.

11. Click Confirm to apply these changes.

